

## Detection of Hog1 Phosphorylation in *Candida albicans* in Response to an Antifungal Protein

Brigitte ME Hayes and Nicole L van der Weerden\*

La Trobe Institute for Molecular Science, La Trobe University, Melbourne, Australia

\*For correspondence: [N.VanDerWeerden@latrobe.edu.au](mailto:N.VanDerWeerden@latrobe.edu.au)

**[Abstract]** It is becoming increasingly apparent that stress signalling is important for tolerance of fungal species to antifungal chemicals and proteins. The high-osmolarity glycerol (HOG) pathway responds to a number of stressors including osmotic and oxidative stress. This protocol describes a method to detect activation of the *Candida albicans* (*C. albicans*) MAPK Hog1 by monitoring its phosphorylation in response to an antifungal protein.

### **Materials and Reagents**

1. *Candida albicans* wild-type (WT)
2. *C. albicans* *hog1Δ/Δ* deletion mutant
3. Half-strength potato dextrose broth (½ PDB) (BD, Difco<sup>TM</sup>, catalog number: 254920)
4. Protein of interest (e.g. the plant defensin NaD1)
5. 5 M NaCl
6. Ultrapure ice-cold water
7. Dry ice
8. 20% trichloroacetic acid (TCA) (20% w/v)
9. 10% trichloroacetic acid (TCA) (10% w/v)
10. 100% ice-cold acetone
11. 4x NuPAGE LDS sample buffer (Life Technologies, catalog number: NP0007)
12. Bond-Breaker TCEP solution (neutral pH) (Thermo Fisher Scientific, catalog number: 77720)
13. 1 M Tris (pH 8.0)
14. Any kD Mini-PROTEAN TGX precast polyacrylamide gels (15 well) (Bio-Rad Laboratories, catalog number: 456-9036)
15. 10x Tris/glycine/SDS running buffer (Bio-Rad Laboratories, catalog number: 161-0072)
16. 5% (w/v) skim milk in TBS
17. Phospho-p38 MAPK (Thr180/Tyr182) antibody (Cell Signaling Technology, catalog number: 9211)
18. Hog1 (y-215) antibody (Santa Cruz, catalog number: sc-9079)

19. Amersham ECL rabbit IgG (HRP-linked antibody from donkey) (GE, catalog number: NA934)
20. Amersham ECL Western blotting detection reagents (GE, catalog number: RPN2106)
21. Yeast peptone dextrose broth (YPD) (see Recipes)
22. Yeast peptone dextrose agar (YPD agar) (see Recipes)
23. Tris-buffered saline (TBS) (see Recipes)
24. Tris-buffered saline with Tween 20 (TBST) (see Recipes)

### **Equipment**

1. 180  $\mu$ m glass beads (acid-washed) (Sigma-Aldrich, catalog number: G1152)
2. Trans-blot turbo mini PVDF transfer pack (Bio-Rad Laboratories, catalog number: 170-4156)
3. 50 ml tubes screw-cap tubes
4. 30 °C shaking incubator
5. Spectrophotometer
6. 500 ml baffled flask
7. Eppendorf 5810 R centrifuge (Eppendorf, catalog number: 5811 000.010)
8. 1.5 ml microfuge tubes
9. Vortex
10. Bench top centrifuge
11. Trans-blot turbo transfer system (Bio-Rad Laboratories, catalog number: 170-4155)
12. Circular mixer
13. Bio-Rad ChemiDoc MP imaging system (Bio-Rad Laboratories, catalog number: 170-8280)

### **Procedure**

- A. Treatment of cells
  1. Plate *C. albicans* wild-type and *hog1Δ* strains onto YPD agar and grow overnight at 30 °C.
  2. Take scraping of both *C. albicans* strains from agar and inoculate 5 ml YPD in a 50 ml tube. Incubate tube overnight at 30 °C (250 rpm).
  3. Dilute both cultures to an OD<sub>600</sub> of 0.2 (in 100 ml ½ PDB) and transfer 100 ml to a 500 ml baffled flask.
  4. Incubate cells at 30 °C (250 rpm) for 5 h (or until they reach an OD<sub>600</sub> of 1.0).

5. Dilute cells to an OD<sub>600</sub> of 1.0. Transfer 10 ml aliquots of each culture to 50 ml tubes. One tube will be required per treatment (see Table 1 for treatment conditions).
6. Treat 10 ml aliquots of WT and *hog1Δ* with NaCl or protein of interest (e.g. 10 µM and 20 µM NaD1 in ultrapure water). Cells will be incubated for 5, 10 or 15 min at 30 °C (250 rpm). For NaCl treatment, add 2.5 ml of 5 M NaCl to the 10 ml of WT or *hog1Δ*.  
For protein treatments, add volume to reach desired protein concentration (e.g. volume of protein for a final concentration of 10 µM or 20 µM). For the *hog1Δ* control treatments, only the 20 µM treatment concentration is required. If no total Hog1 or phosphorylated Hog1 is detected in the *hog1Δ* cells treated with 20 µM protein, then none will be detectable at a lower protein concentration.

**Table 1. Treatment conditions.** Treatment conditions of *C. albicans* WT and *hog1Δ* cells with the protein of interest. 1 M NaCl is included as a positive control. No-protein and *hog1Δ* treatments are included as negative controls.

<i>C. albicans</i> strain	Protein or NaCl concentration	Incubation time
WT	No treatment	-
WT	1 M NaCl	10 min
WT	10 µM protein	5 min
WT	10 µM protein	10 min
WT	10 µM protein	15 min
WT	20 µM protein	5 min
WT	20 µM protein	10 min
WT	20 µM protein	15 min
<i>hog1Δ</i>	No treatment	-
<i>hog1Δ</i>	1 M NaCl	10 min
<i>hog1Δ</i>	20 µM protein	5 min
<i>hog1Δ</i>	20 µM protein	10 min
<i>hog1Δ</i>	20 µM protein	15 min

7. After incubation spin cells down at 1,800  $\times$  g for 5 min (at RT). Discard the supernatant.
8. Resuspend cells in 500 µl ice-cold water. Transfer to a 1.5 ml microfuge tube (Tube A).
9. Centrifuge cells at 3,000  $\times$  g for 5 min (at RT). Discard the supernatant.
10. Freeze pellets with dry ice.

## B. Protein preparation


1. Resuspend cell pellets in 100 µl 20% TCA. Also add approximately 100 µl of 180 µm glass beads. Keep pellets on dry ice.

2. Vortex tubes for 2 min (at highest speed).
3. Transfer supernatant from Tube A to a new tube (Tube B).
4. Wash the remaining beads in Tube A with 500  $\mu$ l 10% TCA. Transfer the 500  $\mu$ l TCA and add it to Tube B.
5. Spin Tube B at 18,000  $\times g$  for 5 min (at RT). Remove supernatant.
6. Resuspend pellets in 1 ml ice-cold acetone.
7. Spin again at 18,000  $\times g$  for 5 min (at RT). Remove supernatant.
8. Resuspend pellets with 50  $\mu$ l loading buffer (1x NuPAGE LDS sample buffer and 50 mM Bond-Breaker). If the buffer turns yellow, add a few microliters of 1 M Tris (pH 8.0) until the color becomes blue.
9. Heat samples at 70 °C for 10 min.

#### C. SDS-PAGE and Western blots

1. Load 25  $\mu$ l of each sample into the wells of a Bio-Rad any kD Mini-PROTEAN TGX precast polyacrylamide gels, 15 well (Gel 1). Repeat this for a second gel (Gel 2).
2. Run gel for 30 min at 200 V (with 1x Tris/Glycine/SDS running buffer).
3. Transfer protein to Trans-blot turbo mini PVDF membranes (from trans-blot turbo mini PVDF transfer pack) using the Bio-Rad trans-blot turbo transfer system (1.3 A, 25 V, 7 min).
4. Block PVDF membranes in 5% skim milk (40 ml TBS, in a 50 ml tube) for 2 h at RT (on a circular mixer). Discard skim milk after incubation.
5. Add primary antibodies and incubate overnight on a circular mixer at 4 °C (in a 50 ml tube).  
For Gel 1, dilute Hog1 (y-215) antibody to 1 in 200 with 10 ml 5% skim milk in TBST.  
For Gel 2, dilute Phospho-p38 MAPK (Thr180/Tyr182) antibody to 1 in 200 with 10 ml 5% skim milk in TBST.
6. Remove primary antibodies. Wash membranes with TBST (3x, 10 min per wash).
7. Dilute secondary antibody (ECL rabbit IgG, HRP-linked) to 1 in 20,000 with 10 ml TBST and incubate with membranes overnight at 4 °C.
8. Remove secondary antibodies. Wash membranes with TBST (3x, 10 min per wash).
9. Mix 1 ml ECL detection reagent 1 and 1 ml of ECL detection reagent 2 for each membrane. Add 2 ml of the mixture to each membrane.
10. Expose membranes using chemiluminescent settings on a Bio-Rad ChemiDoc MP imaging system. Expose membranes for ~ 1 min (or longer if the signal is weak).

See Figure 1 for an example.



**Figure 1. Treatment of *C. albicans* with NaD1 leads to Hog1 phosphorylation.**  
 Western blots showing *C. albicans* Hog1 phosphorylation (detected using Phospho-p38 MAPK antibody) after treatment with the plant defensin NaD1. Bands corresponding to total Hog1 levels are indicated with an arrow. Total Hog1 levels are consistent across all WT treatments and are absent from the *hog1* $\Delta$  mutant. No phosphorylated Hog1 is detected in the no treatment or *hog1* $\Delta$  negative controls. Hog1 phosphorylation is detected in the 1 M NaCl positive control and in all NaD1 treated samples. In this example only one time point is shown for the 20  $\mu$ M NaD1 treated *hog1* $\Delta$  control. Image originally published in Reference 1 (Hayes *et al.*, 2013).

## Recipes

1. YPD or YPD agar
  - 1% yeast extract
  - 2% peptone
  - 2% dextrose
  - If making plates also add 2% agar
2. TBS and TBST
  - 400 mM Tris (pH 7.5)
  - 3 M Tris
  - For TBST also add 0.1% Tween-20

## **Acknowledgments**

This protocol has been adapted from Hayes *et al.* (2013), in which a brief description of the protocol was presented.

## References

1. Hayes, B. M., Bleackley, M. R., Wiltshire, J. L., Anderson, M. A., Traven, A. and van der Weerden, N. L. (2013). [Identification and mechanism of action of the plant defensin NaD1 as a new member of the antifungal drug arsenal against \*Candida albicans\*](#). *Antimicrob Agents Chemother* 57(8): 3667-3675.